

INSTALLATION GUIDE

Remiq AD Sampler (Pro/Lite versions) is distributed as VST3 and Standalone.

Windows

Before you start, close all DAWs before installing Remiq AD Sampler or replacing an older version.

1. Download the Windows Remiq AD Sampler package from the official download link.
2. Open your Downloads folder.
3. If the file is a **.zip** archive, right-click it and choose Extract All, then open the extracted folder.
4. If the package contains an installer, double-click the installer and follow the installation steps.
5. If the package contains a **.vst3** file for manual installation, copy it to the standard Windows VST3 folder:

C:\Program Files\Common Files\VST3

6. Restart your DAW.
7. If your DAW has a plug-in manager or scanner, rescan plug-ins.
8. Remiq AD Sampler should appear in your DAW as a VST3 plug-in.

The current beta package is not digitally signed yet. We are preparing a properly signed installer for the upcoming release.

As a result, Windows may display a SmartScreen warning before running the installer. This is normal for the current beta version.

If Windows SmartScreen blocks the installer:

1. In the SmartScreen warning window, click More info.
2. Check that the app or installer name is related to **Remiq AD Sampler**.

3. Click Run anyway.
4. Continue through the installer.

If Windows security settings block the downloaded file before launch:

1. Right-click the downloaded installer, archive, or extracted file.
2. Choose Properties.
3. Open the General tab.
4. If you see a Security message saying the file came from another computer and might be blocked, enable Unblock.
5. Click Apply.
6. Click OK.
7. Run the installer again or copy the plug-in file again.

After installation

Restart your DAW. If your DAW has a plug-in manager or scanner, rescan plug-ins.

If Remiq AD Sampler does not appear in your DAW:

1. Make sure the plug-in was installed or copied to the standard folders:

`C:\Program Files\Common Files\VST3\Remiq AD Sampler Pro.vst3`

`C:\Program Files\ISINDI Sound\Remiq AD Sampler Pro\Remiq AD Sampler Pro.exe`

`C:\Program Files\Common Files\VST3\Remiq AD Sampler Lite.vst3`

`C:\Program Files\ISINDI Sound\Remiq AD Sampler Lite\Remiq AD Sampler Lite.exe`

2. Open your DAW plug-in manager.
3. Rescan VST3 plug-ins.
4. Restart the DAW.
5. Check whether Remiq AD Sampler appears in the plug-in list.